

Truly,
McKenna

Just Add Stitches!

In Full Bloom



Bridge Over Troubled Waddles Toaster Cover

12" x 10" x 7"

Before Getting Started:

Read all instructions before beginning this project to find valuable tips, save time and minimize mistakes by understanding the process before you begin!

Truly McKenna Art Prints are not pre-shrunk. If you are making a project that will be washed after use, you may want to pre-wash your fabrics.

The term WOF refers to width of fabric.

Use an accurate $\frac{1}{4}$ " seam allowance unless instructed otherwise in pattern directions.

We strive to create accurate patterns, but just as no tree in nature is perfect, neither are we. Visit our website at www.pineneedles.com for any corrections before beginning your quilt.



Materials Needed:

- One IFB07-P *Bridge Over Troubled Waddles Truly McKenna* Panel
- Fabric 1: MR1-170 Meadow - 1 yard for Backing, Lining, Gusset and Optional Side Pockets
- Fabric 2: 1895-227 Sprout - $\frac{1}{4}$ yard for Binding
- Cotton Batting - $\frac{1}{2}$ yard

Preparing Panel and Fabric:

- The *Bridge Over Troubled Waddles* Panel will be cut into **TWO** 13" x 11" sections. Choose sections that are pleasing to you. There is **NOT** much waste, be careful to measuring correctly. You should end up with TWO sections that measure 13" x 11".
- Fabric 1:
 - Cut 2 - 13" x 11" rectangles for Lining
 - Cut 2 - 8" x 28" rectangles for Gusset
 - Cut 2 - 7" x 10" pieces for Pockets *Optional
- Fabric 2: Cut 3 - 2 $\frac{1}{2}$ " x WOF strips for Binding
 - Sub cut one strip into:
 - 2 - 2 $\frac{1}{2}$ " x 11" strips
 - 2 - 2 $\frac{1}{2}$ " x 7" strips *Optional, for Pockets
- Cotton Batting:
 - Cut 1 - 8" x 28" strip
 - Cut 2 - 13" x 11" rectangles

Toaster Cover Front:

1. Layer one 13" x 11" lining fabric right side down, one 13" x 11" batting rectangle and the 13" x 11" *Bridge Over Troubled Waddles* front panel piece right side up.
2. Quilt as desired.
3. Round top corners using template.
4. Trim quilted panel to 12" x 10".
5. Bind bottom edge with one of the 11" Binding strips.


Toaster Cover Back:

1. Layer the remaining 13" x 11" lining fabric right side down, the 13" x 11" batting rectangle and the 13" x 11" *Bridge Over Troubled Waddles* back panel piece right side up.
2. Quilt as desired.
3. Round top corners using template.
4. Trim quilted panel to 12" x 10".
5. Bind bottom edge with the remaining 11" Binding strip.

Template for Rounded Corners

Gusset:

1. Layer one 8" x 28" Gusset rectangle right side down, the 8" x 28" strip of batting and the remaining 8" x 28" Gusset rectangle right side up.
2. Quilt as desired.
3. Trim Gusset to 7" x 27".
4. Pockets: *Optional
 - a. Iron each 7" x 10" Pocket piece in half, creating 2 - 5" x 7" rectangles.
 - b. Bind the top 7" edge of each Pocket piece.
 - c. Place a 5" x 7" pocket on each end of the gusset and baste sides in place.
5. Bind the bottom 7" edge of Gusset/Pocket.



Assembly:

1. Using the Toaster Cover Front and the Gusset, baste edges together with right sides out. Ease in around the rounded corners. Seams will be on the outside.
2. Repeat the same process with Toaster Cover Back and remaining edge of the Gusset.
3. Bind the front edge of the Toaster Cover Front and the back edge of Toaster Cover Back.
4. Wrap binding over towards the Gusset and machine or hand stitch to in place.

The Pockets are perfect for toaster tongs or small napkins!

